Introduction to Virtual Memory Computer Operating Systems, Spring 2025

Instructors: Joel Ramirez Travis McGaha

Head TAs: Ash Fujiyama Emily Shen Maya Huizar

TAs:

Ahmed Abdellah Bo Sun Joy Liu Susan Zhang Zihao Zhou

Akash Kaukuntla Connor Cummings Khush Gupta Vedansh Goenka

Alexander Cho Eric Zou Kyrie Dowling Vivi Li

Alicia Sun Haoyun Qin Rafael Sakamoto Yousef AlRabiah

August Fu Jonathan Hong Sarah Zhang Yu Cao



pollev.com/cis5480

What's the vibe?

Administrivia

PennOS

- Milestone 0, which should have been done last week
- Everyone should have already contacted their group, and should get started working on it.
 - · IF THIS ISN'T TRUE LET US KNOW BECAUSE????????
- Milestone 1 is due next week
 - APRIL 11TH
 - Need to meet with TA again to show significant progress (60 %)
 - Have a plan (a REAL plan) for how to complete the rest
- Full Thing due ~April 25TH

Administrivia

- Exam grades posted
 - Remember the Clobber Policy. Many people benefit from this policy in our courses
 - Regrade are open and will stay open till April 5th at midnight.
- Penn-Shell & Midterm Regrades
 - Should get them all done by the end of Monday!

Lecture Outline

- Problems with Old Memory Model
- Virtual Memory High Level
- Address Translation

Poll Everywhere

pollev.com/cis5480

- What does this print for x at all three points?
- How does the value of ptr change?


```
6 int main() {
    int x = 3;
    int *ptr = &x;
    printf("[Before Fork]\t x = %d\n", x);
    printf("[Before Fork]\t ptr = %p\n", ptr);
    pid_t pid = fork();
    if (pid < 0) {
      perror("fork errored");
      return EXIT FAILURE;
    if (pid == 0) {
      x += 2;
      printf("[Child]\t\t x = %d\n", x);
      printf("[Child]\t\t ptr = %p\n", ptr);
      return EXIT_SUCCESS;
    // assume no error
    waitpid(pid, NULL, 0);
    x -= 2;
    printf("[Parent]\t x = %d\n", x);
    printf("[Parent]\t ptr = %p\n", ptr);
33
    return EXIT_SUCCESS;
```

Review: Processes


 Definition: An instance of a program that is being executed (or is ready for execution)

Consists of:

- Memory (code, heap, stack, etc)
- Registers used to manage execution (stack pointer, program counter, ...)
- Other resources




Multiprocessing: The Illusion



- Computer runs many processes simultaneously
 - Applications for one or more users
 - Web browsers, email clients, editors, ...
 - Background tasks
 - Monitoring network & I/O devices


Multiprocessing: The (Traditional) Reality



- Single processor executes multiple processes concurrently
 - Process executions interleaved (multitasking)
 - Address spaces managed by virtual memory system (later in course (now!))
 - Register values for non-executing processes saved in memory

Memory As We Know It


The CPU directly uses an address to access a location in memory




Problem 1: How does everything fit?

On a 64-bit machine, there are $^{\sim}2^{64}$ *Addressable bytes*, which is: 18,446,744,073,709,551,616 Bytes (1.844 x 10)

Laptops usually have around 8GB which is 8,589,934,592 Bytes (8.589 x 10⁹)




Problem 2: Sharing Memory



- How do we enforce process isolation?
 - Could one process just calculate an address into another process?


Problem 2: Sharing Memory

- How do we enforce process isolation?
 - Could one process just calculate an address into another process?




Problem 3: How do we segment things

- A process' address space contains many different "segments" that have specific functionality.
- Problem: How do we keep track of the location and permissions (Read/Write) each segment may have?
 - (e.g., that Read-Only data can't be written)



The real question is who is keeping track of this?

Problem 3: How do we segment things?




Note: some mappings are missing, not enough space.

Lecture Outline

- Problems with Old Memory Model
- Virtual Memory High Level
- Address Translation

This Is Not What Happens

The CPU directly uses an address to access a location in memory



Indirection

- "Any problem in computer science can be solved by adding another level of indirection."
 - David wheeler, inventor of the subroutine (e.g. functions)
- The ability to indirectly reference something using a name, reference or container instead of the value itself. A flexible mapping between a name and a thing allows chagcing the thing without notifying holders of the name.
 - May add some work to use indirection
 - Example: Phone numbers can be transferred to new phones
- Idea: instead of directly referring to physical memory, add a level of indirection


Idea:

- We don't need all processes to have their data in physical memory, just the ones that are currently running
- For the process' that are currently running: we don't need all their data to be in physical memory, just the parts that are currently being used
- Data that isn't currently stored in physical memory, can be stored elsewhere (disk).
 - Disk is "permanent storage" usually used for the file system
 - Disk has a longer access time than physical memory (RAM)

Pages

Pages are of fixed size $\sim 4KB$ $4KB \rightarrow (4 * 1024 = 4096 bytes.)$

Memory can be split up into units called "pages"



Definitions

Sometimes called "virtual memory" or the "virtual address space"

- Addressable Memory: the total amount of memory that can be theoretically be accessed based on:
 - number of addresses ("address space")
 - bytes per address ("addressability")

IT MAY OR MAY NOT EXIST ONHARDWARE (like if that memory is never used)

Physical Memory: the total amount of memory that is physically available on the computer


Physical memory holds a subset of the addressable memory being used

Virtual Memory: An abstraction technique for making memory look larger than it is and hides many details from the programs.

Virtual Address Translation

THIS SLIDE IS KEY TO THE WHOLE IDEA

Programs don't know about physical addresses; virtual addresses are translated into them by the MMU



Page Tables

More details about translation later

- Virtual addresses can be converted into physical addresses via a page table.
- There is one page table per processes, managed by the MMU


Virtual page #	Valid	Physical Page Number
0	0	null //page hasn't been used yet
1	1	0
2	1	1
3	0	disk

Valid determines if the page is in physical memory

If a page is on disk, MMU will fetch it

Page Fault Exception

- An Exception is a transfer of control to the OS kernel in response to some synchronous event (directly caused by what was just executed)
- In this case, writing to a memory location that is not in physical memory currently



Problem: Paging Replacement

More details about page replacement later

- We don't have space to store all active pages in physical memory.
- If physical memory is full and we need to load in a page, then how do we choose a page in physical memory to store on disk in the swap file
- If we need to load in a page from disk, how do we decide which page in physical memory to "evict"
- Goal: Minimize the number of times we have to go to disk. It takes a while to go to disk.




Poll Everywhere

pollev.com/cis5480

CIS4480, Spring 2025


What happens if this process tries to access an address in page 3?





pollev.com/cis5480

What happens if we need to load in page 1 and physical memory is full?



Lecture Outline

- Problems with old memory model
- Virtual Memory High Level
- Address Translation

Aside: Bits

- We represent data on the computer in binary representation (base 2)
- A bit is a single "digit" in a binary representation.
- A bit is either a 0 or a 1

- ❖ In decimal -> 243
- In binary -> 0b11110011

Hexadecimal

- Base 16 representation of numbers
- Allows us to represent binary with fewer characters
 - <u>0b</u>11110011 == <u>0x</u>F3
 <u>b</u>inary
 h<u>ex</u>

Decimal	Binary	Hex	
0	0000	0x0	
1	0001	0x1	
2	0010	0x2	
3	0011	0x3	
4	0100	0x4	
5	0101	0x5	
6	0110	0x6	
7	0111	0x7	
8	1000	0x8	
9	1001	0x9	
10	1010	0xA	
11	1011	0xB	
12	1100	0xC	
13	1101	0xD	
14	1110	0xE	
15	1111	0xF	

pollev.com/cis5480

Poll Everywhere

- ❖ A page is typically 4 KiB -> 2¹² -> 4096 bytes
- If physical memory is 32 KiB, how many page frames are there?

A. 5 B. 4 C. 32 D. 8 E. We're lost...

If addressable memory for a single process consists of 64 KiB bytes, how many pages are there for one process?

A. 64 B. 16 C. 20 D. 6 E. We're lost...

If there is one page table per process, how many entries should there be in a single page table?

A. 6 B. 8 C. 16 D. 5 E. None of These...

Addresses

- Virtual Address:
 - Used to refer to a location in a virtual address space.
 - Generated by the CPU and used by our programs
- Physical Address
 - Refers to a location on physical memory
 - Virtual addresses are converted to physical addresses

64 bits:

Page Offset

- This idea of Virtual Memory abstracts things on the level of Pages
 - $(4096 \text{ bytes} == 2^{12} \text{ bytes})$
- On almost every machine, memory is byte-addressable meaning that each byte in memory has its own address
- How many distinct addresses can correspond to the same page?

At a minimum, how many bits are dedicated to calculating the location (offset) of an address within a page?

pollev.com/cis5480

Poll Everywhere

If there are 16 pages (virtual), how many bits would you need to represent the number of pages?

If there are 8 pages frames (physical), how many bits would we need to represent the number of page frames?

Page bits	Frame bits
4. 4	2
B. 4	3
C. 3	3
D. 5	3

E. We're lost...

High Level: Steps For Translation

- Derive the virtual page number from a virtual address
- Look up the virtual page number in the page table
 - Handle the case where the virtual page doesn't correspond to a physical page frame
- Construct the physical address

Address Translation: Virtual Page Number


- A virtual address is composed of two parts relevant for translating:
 - Virtual Page Number length = bits to represent number of pages
 - Page offset length = bits to represent number of bytes in a page

Virtual Page Number	Page Offset
---------------------	-------------

- The virtual page number determines which page we want to access
- The page offset determines which location within a page we want to access.
 - Remember that a page is many bytes (~4KiB -> 4096 bytes)

Virtual Address High Level View

- High level view:
 - Each page starts at a multiple of 4096 (0X1000)
 - If we take an address and add 4096 (0x1000) we get the same offset but into the next page



Address Translation: Virtual Page Number

- A virtual address is composed of two parts relevant for translating:
 - Virtual Page Number length = bits to represent number of pages
 - Page offset length = bits to represent number of bytes in a page

pollev.com/cis5480

Virtual Page Number

Page Offset

- Example address: 0x1234
 - What is the page number?
 - What is the offset?
 - Reminder: there are 16 virtual pages, and a page is 4096 bytes

Address Translation: Lookup & Combining

Once we have the page number, we can look up in our page table to find the corresponding physical page number.

For now, we will assume there is an associate page frame

Virtual page #	Valid	Physical Page Number
0x0	0	null
0x1	1	0x5

With the physical page number, combine it with the page offset to get the physical address

Physical Page Number	Page Offset
----------------------	-------------

- Since we only need 3 bits to represent the physical page number, we only need 15 bits for the address (as opposed to 16).
- In our example, with 0x1234, our physical address is 0x5234

Translation Done!

Page Faults

What if we accessed a page whose page frame was not in physical memory?

Virtual page #	Valid	Physical Page Number
0x0	0	null
0x1	1	0x0
0x2	1	0x5
0x3	0	Disk

In this example, Virtual page 0x3

Page Faults

Virtual page #	Valid	Physical Page Number
0x0	0	null
0x1	1	0x0
0x2	1	0x5
0x3	0	Disk

- In this example, Virtual page 0x3, whose frame is on disk (page 0x3 handled before, but was evicted at some point)
 - MMU fetches the page from disk
 - Evicts an old page from physical memory if necessary
 - Uses LRU or some page replacement algorithm
 - Writes the contents of the evicted page back to disk
 - Store the previously fetched page to physical memory

Page Faults

Virtual page #	Valid	Physical Page Number
0x0	0	null
0x1	1	0x0
0x2	1	0x5
0x3	0	Disk
	•••	

- In this example, Virtual page 0x0, which has never been accessed before
 - Evict an old page if necessary (A page that isn't needed)
 - Claim an empty frame and use it as the frame for our virtual page